

Capture Technical Support Guide

Title of Guide

Summary


This guide will show how to add a device to Capture VS

Requirements

- Capture device initialized and set up on a network
- Device username and password
- Capture VS installed


Instructions

1. Open Capture VS. Press the + in the top right of the screen to Add a Device




Capture Technical Support Guide

2. Select SN/Scan




Capture Technical Support Guide

3. Scan the QR code for the device and the Serial Number will be automatically entered. You can also select Manually Enter SN.




Capture Technical Support Guide

4. Tap Next




Capture Technical Support Guide

5. Select the Device Type



Capture Technical Support Guide

6. Enter Device Information
 - Device Name will be how the device shows in the app
 - Enter Username/Password for the device
 - Tap Save



Capture Technical Support Guide

After a few moments the device will connect to Live View and can be accessed in the Home tab of Capture VS

